

FIRST COMPUTER LIBRARY

COMPUTER FUN

Gaby Waters
Illustrated by Graham Round




Additional programs by Paul Shreeve Series Editor: Helen Davies


Contents

3	About this book	32	Number puzzle programs
4	Typing in programs	34	Geography quiz
6	What to do if things go wrong	35	Times table quiz
8	Happy Birthday	36	Adding sound and colour
10	Space monsters	38	Puffing train graphics
12	Red Alert	40	Program conversions:
14	Drawing pictures		BBC and Commodore 64
16	Computer Snap	42	Program conversions:
18	Code-writer		Electron and VIC 20
20	Puffing train program	44	Program conversions:
22	Computer postcard		Spectrum
24	Birthday fact-finder	45	Program conversions:
26	Star racer		Apple
28	Obstacle course game	47	Bug-spotting guide
30	Find the key	48	Index
	The state of the s		






The programs are written in a computer language called BASIC. Each home computer understands a slightly different version of BASIC and you will need to change some program lines to suit your computer. These lines are clearly marked and on pages 40-46 there are lists of line changes for Spectrum, BBC, Electron, Commodore 64, VIC 20 and Apple computers.



Typing in programs

To make a computer do something, you need to type in a list of instructions called a program. Programs for home computers are written in BASIC. BASIC is quite like English, with some special words and symbols. Below you can see what a program written in BASIC looks like.



This program will make a computer ask your name and then put a message on the screen. Each instruction in the program is on a separate

line and each line begins with a number. The numbers make the computer carry out the instructions in the right order.


How to type in a program



When you switch on a computer, a symbol called a cursor flashes on the screen. This means that you can start typing in a program.



At the end of each line, press the key marked RETURN, or ENTER. This puts the program line into the computer's memory.



Type the program just as it is printed. On most computers you type BASIC commands letter by letter, but on some you just press one key.



If you make a mistake, rub it out by pressing the delete key. The label on the key varies from one make of computer to another.

Running the program

When you have finished typing in the program, you type the command RUN and press RETURN (or ENTER). This is called running the program and it makes the computer carry out your instructions. RUN does not need a line number because it is not part of the program.



If you typed in the program on the opposite page, try running it. First the computer will ask your name. Type it in and press RETURN (or ENTER). Then the computer will give you a



message. You can make the computer run the program again by typing RUN again and pressing RETURN (or ENTER). Try it a few more times, using different names.


Getting rid of the program



When you have finished with the program, just type NEW and press RETURN (or ENTER). This wipes the instructions from the computer's memory so it is ready for you to type in another program.

What to do if things go wrong

If a program does not work you have probably made a mistake typing it in. It is very easy to make mistakes when you type in programs. Mistakes in programs are called bugs. Some computers let you know if there is a bug in a program line when you press RETURN or ENTER, but most wait until you try to run the program.



The computer tells you there is a bug in a program by putting a special message on the screen like the one above. This is called an error message. It usually tells you what sort of mistake it is and

what line it is in. Error messages are different on different computers and are often written in a sort of code. To find out what they mean, look in your computer's manual.

This is the bug.

PRINT is spelt

wrongly.

IØ PRINT"HELLO"

20 PRONT "FRIEND" 2Ø PRINT "FRIEND"

How to de-bug a program



First type LIST and press RETURN* to display the program lines on the screen. Then check through the program lines for mistakes.




Bugs are not easy to find, but it is easier to spot them if you know what to look for. The bug spotting guide on page 47 gives you some handy tips and hints.


When you spot the bug, type the whole line again and press RETURN. Now if you list the program again, you will see that the new line has replaced the old one.

Changing a program

In this book there are lots of ideas for adapting programs by adding or changing program lines. You do this in a similar way to de-bugging, as shown below.



First type LIST and press
RETURN to put the program
lines on the screen. To
change a line, type in the line
number and the new
instruction and press
RETURN.



You add extra lines to programs in the same way. Their line numbers tell the computer where to put them in the program.

Special words


Most BASIC commands are understood by all computers but there are some which vary from computer to computer. In this book, lines with commands which vary are printed on a red stripe. In the boxes below you can find out what to do when you come across one of these.




When you see a line printed on a red stripe, turn to the conversion pages at the back of the book. Find the page for your computer, then look for the name and page number of the program you are typing in.




If the line needs changing for your computer, you will find a conversion line with the same line number. Type this line instead of the one on the




stripe. If there is no conversion line, this line does not need changing for your computer and you can type the line on the stripe, just as it is.






You can change the birthday message by typing different words inside the quotes in lines 20, 90 and 100. To do this, type LIST and press RETURN to put the program lines on the screen. Then retype the lines you want to change. In the pictures above there are some ideas for changing the message or you can invent messages of your own.



Now try adding the lines above to the program. They make the computer print the message again and again until you stop the program, or switch off the computer. You can find out how to stop the program on the right.



You can make the computer stop running a program by pressing the ESCAPE key. The label on this key varies on different computers. You can find out what your computer calls it by looking on page 46 of this book or in your computer's manual.

Space monsters

This program makes a picture of a computer space monster on your screen. The monster shape is made up of X's, so you must be careful to type all the X's and the spaces in the right place. The design on the paper below will help you to count the number of X's and spaces in each line. In the program the spaces are marked with the symbol \square . For each \square , press the space bar once.

Remember to check line 10 in the conversion pages.

There are

5 spaces

here.

Space monster program

10 CLS

- 20 PRINT:PRINT:PRINT
- 30 PRINT "00000X0X"
- 40 PRINT "GOODXXXXXX"
- 50 PRINT "0000X0X0X"
- 60 PRINT "DDDDXXXXXX"
- 70 PRINT "XXXXXXXXXXXXXXXX"
- 80 PRINT "XXDDXXXXXXDDXX"
- 90 PRINT "XXDDOXOXDDOXX"
- 100 PRINT "0000XX0XX"

There are 13 X's here. Use this drawing of the monster to help you count the X's and spaces.

XX

X

X

x


XX

XX

XXX

Running the program

Type RUN to make the program work. If your monster looks wrong, type LIST and press RETURN and check the program lines to make sure you have the right number of X's and spaces.




The monster may look smaller on your screen.

X

Making the monster move

If you add the program lines printed below you can make the monster wave its arms up and down. To do this, first type LIST followed by RETURN to put the program lines on the screen, then type in the extra lines. Make sure you type each line exactly as it is printed and press the space bar every time you see the symbol \square .

230 GOTO 10



5 spaces


here.



Design your own monster

1 Try making the monster look different by using letters such as O or S instead of X's. To do this, retype all the lines starting with PRINT, using your letter instead of the X's.

-	1			T	F	T	Т	-	1	T	I	T
		1	x		L	t	İ		X	I		I
,				X				X	L		L	L
					8	8	8					L
	8	8	8	8		8		8	8	8	8	Т
	8			8	8	8	8	8	Γ		8	
	8				8	8	8				8	T
8	8										8	8



If you like, you can make a new monster of your own. Design the monster on a piece of squared paper like this. Then type NEW and press RETURN. Type the program again putting the letters and spaces from your design in quotes in PRINT lines.

Red Alert

The program on this page puts a flashing "Red Alert" message on the screen. Try typing it into your computer.



20 FOR K=1 TO 300: NEXT K

30 PRINT:PRINT:PRINT

40 PRINT TAB(3); "DANGER"

50 PRINT TAB(3);"RED ALERT"

60 FOR K=1 TO 300:NEXT K

70 GOTO 10

Running the program

Type RUN to start the program working. To stop the program, press ESCAPE (or your computer's key).

Changing the program

In the boxes below there are some ideas for changing the program. To change the program, stop it running and type LIST. Then type in the new versions of the lines you want to change.



Type this in lines 20 and 60 to make the message flash faster.

FOR K=1 TO 150:NEXT K

Type this in lines 20 and 60 to make the message flash more slowly.

You can make the message flash at a different speed by changing the number 300 in lines 20 and 60. A smaller number makes it flash quickly and a larger number makes it flash slowly.

Look at the conversion pages to see if you need to change this line.

RED ALER

The message will carry on flashing until you stop the program.

2

40 PRINT TAB(14);"DANGER"

50 PRINT TAB(8); "RED ALERT"


Try these numbers.



You can move the message further across the screen by putting a bigger number in brackets after TAB in lines 40 and 50. The number tells the computer how many spaces to leave before the words on the screen.

More things to do







Next time you go into a computer shop try typing the program, with a message like this, into one of the shop's computers.

Personal messages

You can make the computer send a flashing message addressed to you, or whoever is running the program, by adding the lines on the right. To do this, stop the program, type LIST and then type in the new lines. You can find out how the new program works below.

2 CLS

- 4 PRINT "WHAT IS YOUR NAME?"
- 6 INPUT N\$
- 40 PRINT TAB(3):N\$:" IS GREAT"
- 50 PRINT TAB(3); N\$;" RULES O.K."




First the computer asks you your name. You should type it in and press RETURN.

Then the computer flashes these messages with your name in them on the screen.




Try the program on your friends or make up some other names to type in.




When you type RUN the screen will go blank. To start drawing, press any key. A star will appear on the screen. To draw a line of stars going up the screen, press A. To draw a line going down, press Z. To draw lines left and right press N and M. Try making patterns on your screen. To stop the program, press the key marked ESCAPE (or your computer's key).

Rubbing out stars




These extra program lines enable you to rub out the last star you put on the screen by pressing the space bar. Before you type in the extra lines, stop the program and type LIST to put the program on the screen.

Printing spaces



You can make a row of spaces by pressing one of the direction keys, then the space bar, several times. This is very useful for drawing pictures that need breaks in the lines.



You can draw patterns with different symbols, such as & or #. To do this, list the program again and type in these new lines. Now when

B

you run the program, the computer starts by asking you what symbol you want to use, as shown on the screen above.



Computer Snap

You can make your computer play Snap by typing in the program on the right. Remember to check the conversion pages to see whether you need to change any of the lines on the red stripes. You can find out how to play the game opposite.

Leave a space inside the quotes before the words WELL DONE.

Snap program

10 CLS

20 LET N=0:PRINT:PRINT:PRINT

30 LET X=INT(RND(1)*10+1)

40 LET Y=INT(RND(1) * 10+1)

50 PRINT X;" ";Y; -

60 LET AS=INKEYS

70 LET N=N+1

80 IF A\$="S" AND X=Y THEN GOTO 110

Type two spaces

line 50.

inside the quotes in

90 IF N<=100 THEN GOTO 60

100 GOTO 10

110 PRINT " WELL DONE"


120 FOR K=1 TO 1000:NEXT K

130 GOTO 10

Changing speed

You can change the speed of the game very easily by altering the number 100 in line 90. A bigger number makes the game slower and a smaller number makes it faster. Try changing line 90 as shown in the boxes on the right. If the game is still not the right speed for you, try other numbers in line 90.







When you run the program, the computer puts a pair of numbers on the screen as shown in the picture above.



Then it puts another pair on the screen, and another, and so on, changing the numbers each time.

When the two numbers are the same, try and press the S key (for Snap) before the new numbers appear on the screen.

> You only need to change this line if you have a Spectrum.

Word and number snap



You can change the game so that the computer writes the first number as a word. To do this, add the program

2 DIM NS(10)-4 FOR K=1 TO 10 6 READ NS(K): NEXT K 50 PRINT N\$(X);" ";Y; 140 DATA "ONE", "TWO", "THREE", "FOUR" 150 DATA "FIVE", "SIX", "SEVEN"

160 DATA "EIGHT", "NINE", "TEN"

lines in the box above. First stop the program, then list it and type in the new lines. If you find the new game is too

fast, you can change the


speed again to make it slower.

Code-writer

Here is a program to make a computer code and decode messages. You can use it to send top-secret information, or write private letters to your friends.

Nobody will be able to crack the code without this program and the line changes shown

opposite.



How to use the program



When you run the program, the computer asks you to type in your message.



You should type it in and then press RETURN.



The computer translates your message into code and puts it on the screen.

Exchanging secret messages



If any of your friends have a computer you can exchange messages in code. You can pass them to one another by leaving them in a secret



hiding place. Spies call this a dead letter box. Your friend can pick up your messages when the coast is clear.




To read the messages you have to decode them back into English. You can find out how to change the program to do this below.


19

Decoding messages

To decode secret messages you need to change lines 30 and 110 of the code program. List the program and type in the new lines on the right. You can try out the decoding program with the coded messages in the pictures below.







Adding a railway track

The program lines on the right put a railway track on the screen for the train to run along. To add them to your program, type LIST. Then type the new lines.

23 FOR X=A TO B+10

27 NEXT X

Look at the conversion pages to see if you need to change this line.

The computer draws a track like this on the screen.

Changing direction

115 IF X+16>=A+10 THEN GOTO 120

117 PRINT TAB(X+16,3);"

140 LET AS-INKEYS

150 IF A\$="" THEN GOTO 140

160 IF A\$="P" THEN GOTO 20

170 LET Z=A:LET A=B:LET B=Z:LET C=-1

180 GOTO 30


You can make the train move backwards as well as forwards by adding the new lines shown above.



Now when you run the program, you press the Q key to make the train move



backwards and the P key to make it move forwards.



On pages 38-39 you can find out how to make the computer draw a more realistic looking train using special computer graphics commands.



The program below will help you write holiday postcards. You could use it to make joke postcards and send them to your friends.



Dear Deadeye Dick,
I am having a fantastic
the weather is very hot
wish you were here
love from Shiny Sid

MR DEADEYE DICK
PIRATE PLACE
TREASURE ISLAND

10 CLS

- 20 PRINT "WHERE ARE YOU?":INPUT P\$
- 30 PRINT "WHAT SORT OF TIME"
- 40 PRINT "ARE YOU HAVING?":INPUT D\$
- 50 PRINT "DESCRIBE THE WEATHER"
- 60 INPUT W\$
- 70 PRINT "AND THE FOOD":INPUT F\$
- 80 PRINT "WHAT'S YOUR NAME?": INPUT N\$
- 90 PRINT "WHO ARE YOU WRITING TO?"
- 100 INPUT A\$

110 CLS

- 120 PRINT:PRINT "DEAR ";A\$;",":PRINT
- 130 PRINT "I AM HAVING A ":D\$
- 140 PRINT "TIME HERE IN ";P\$;"."
- 150 PRINT "THE WEATHER IS "; W\$
- 160 PRINT "AND THE FOOD IS ";F\$;"."
- 170 PRINT "WISH YOU WERE HERE!"
- 180 PRINT:PRINT "LOVE FROM ";N\$




When you run the program, the computer asks questions about your holiday. Type in your answers, pressing RETURN after each one. Then the computer clears the screen and writes a message using your answers.



You can turn the postcard program way as the you letter program. To change the program you type in the lines in the box below. The new one above.

program works in the same way as the postcard program. The computer makes up a message for a letter, like the one above.

If you have a cassette recorder, you can save the program on tape and use it each time you want to write a thank-you letter.





Birthday fact-finder

Computers are very good at calculations and the program below will make a computer calculate how old you are in years, months and days. Try using the program to find out your exact age. Then you can add extra program lines to work out your age in the year 2000 and the day of the week that you were born on.

10 CLS:DIM N(12)

- 20 FOR K=1 TO 12:READ N(K):NEXT K
- 30 PRINT "WHAT IS TODAY'S DATE?"
- 40 INPUT D1,M1,Y1
- 50 PRINT "WHEN WERE YOU BORN?"
- 60 INPUT D2,M2,Y2:LET DA=D1-D2
- 70 LET MA=M1-M2:LET YA=Y1-Y2
- 80 IF DA>=0 THEN GOTO 100
- 90 LET DA=DA+N(M1):LET MA=MA-1
- 100 IF MA>=0 THEN GOTO 120
- 110 LET MA=MA+12:LET YA=YA-1
- 120 IF YA/4<>INT(YA/4) THEN GOTO 140
- 130 IF M1=3 AND M2=2 THEN LET DA=DA+1
- 140 PRINT "YOUR AGE TODAY IS"
- 150 PRINT YA;" YEARS ";MA;" MONTHS"
- 160 PRINT DA;" DAYS"
- 500 DATA 31,31,28,31,30,31
- 510 DATA 30,31,31,30,31,30

This jump in the line numbers enables you to add extra lines later.




Year 2000


170 PRINT " IN YEAR 2000 YOU WILL BE" 180 PRINT " ";2000-Y2;" YEARS OLD"

If you add these lines to the program, the computer will work out how old you will be in the year 2000.

Using the program



First the computer asks you today's date. You must type the date in figures as shown below.




First type the day of the month and press RETURN. Then type the month and press RETURN and then the year and press RETURN.



When the computer asks, type your date of birth in the same way. The computer will do a quick calculation and tell you exactly how old you are.





100 IF R=1 THEN LET X(K)=X(K)+1

130 PRINT:PRINT "NUMBER ";Y;" WINS"
Running the race


110 NEXT K

1 2 3 4 5 6

When you run the program, the computer puts six stars on the left side of the screen. These are the "runners" in the race and they are numbered 1 to 6.




The stars race each other across the screen and the first to reach the right wins. Every time you run the race the computer changes the speed of each star.




When the race is over, run the program a few more times and you will see that there is usually a different winner each time.

Adding a race track




If you add these lines to the program, the computer will make a race track for the stars.



Now when you run the program, the computer starts by putting the race track on the screen and the stars move across the screen inside their own lanes.

Race game

You can turn the race into a game you can play with a friend by adding the lines below to the program. The new program lets you both guess the winner before the race starts. You can see how it works in the boxes on the right.



Playing the game



First the computer asks each of you your name. Type it in and press RETURN.



Then it asks for your guesses. Choose a star and type in its number. If your star wins, the computer sends you a message after the race. To play again, press RETURN.

Obstacle course game

In this game you have to pit your wits against the computer as you steer a star round obstacles on the screen. Try it and see if you can complete the course. Then you can add some program lines to make the game more difficult.




On some computers you need to add extra lines to this program so check the conversion pages.

- 30 LET Q=1:LET W=15
- 50 IF Z(Q,W)=1 THEN PRINT "CRASH":STOP
- 60 IF A=Q THEN PRINT "WELL DONE":STOP

- 110 IF A\$="A" THEN LET W=W-1
- 120 IF A\$="Z" THEN LET W=W+1
- 130 IF A\$="M" THEN LET Q=Q+1



To have another go, type RUN.



How to play


As soon as you type RUN a star appears on the left of your screen as shown in the picture above.

Then the screen starts filling up with small squares. You must move the star across the screen avoiding all these "obstacles".


To move the star, there are 3 control keys. Press the A key to move the star up, Z to move it down and M to move it across to the right.

On the Apple, the obstacles are 0's instead of squares.


Improving the game



These pictures show what the game looks like when you add the lines below to the program. First the computer draws a "wall" round the edge of the screen with a gap in each side.



The star is in the gap on the left and the gap on the right is the goal. The computer starts filling the area inside the walls with the obstacle blocks.



To win the game you must steer the star through the blocks and into the goal on the right. If you bump into an obstacle or the wall, you lose the game.

Adding the extra lines

To play the new version of this game, type in the lines on the right. Check the conversion pages to see whether you need to change lines 32 and 34 to suit your computer.

On page 37 you can find out how to add sound effects to this game.

- 22 FOR K=1 TO A:LET Z(K,1)=1
- 24 LET Z(K,B)=1:NEXT K
- 26 FOR L=1 TO B:LET Z(1,L)=1
- 28 LET Z(A,L)=1:NEXT L
- 31 LET Z(Q,W)=0
- 32 LET Z(A,INT(RND(1) * 15+3)) = 2
- 33 FOR L=1 TO B:FOR K=1 TO A
- 34 IF Z(K,L)=1 THEN PRINT TAB(K,L);Z\$
- 35 NEXT K: NEXT L
- 60 IF Z(Q,W)=2 THEN PRINT "WELL DONE":STOP







Find the key program

- 10 CLS:LET N=0:LET A=ASC("A")
- 20 LET X=INT(RND(1) * 26+A)
- 30 PRINT:PRINT "FIND ";CHR\$(X)
- 40 LET AS=INKEY\$
- 50 IF A\$="" THEN LET N=N+1:GOTO 40
- 60 IF A\$<>CHR\$(X) THEN GOTO 120
- 70 LET S=INT((N/235) * 10)/10

Line 70 is different for most computers so make sure you check the conversion pages.



- 80 PRINT "YOU TOOK ";S;" SECONDS"
- 90 PRINT "PRESS RETURN TO CONTINUE"
- 100 INPUT R\$
- 110 GOTO 10
- 120 PRINT "WRONG KEY": GOTO 90

If you have a Spectrum type ENTER instead of RETURN.

Improving the game

To make the game better, you can add the lines on the right. Now when you want to finish the game, type STOP and press RETURN. When you do this, the computer will tell you your best time, worst time and your average speed for finding the keys.

В

- 5 LET B=100:LET W=0
- 7 LET T=0:LET K=0
- 74 IF S<B THEN LET B=S
- 75 IF S>W THEN LET W=S
- 76 LET T=T+S:LET K=K+1
- 105 IF R\$="STOP" THEN GOTO 130
- 130 LET T=T/K:LET A=(INT(T*10))/10
- 140 PRINT "BEST TIME :";B;" SECONDS"
- 150 PRINT "WORST TIME:";W;" SECONDS"
- 160 PRINT "AVERAGE :"; A; " SECONDS"



Number puzzle programs The programs on these two pages are for number of

games. In Guess the number the computer chooses a number and you have to try and guess it. In Mindreader you choose a number and the computer works out what it is.

Guess the number

- 10 CLS
- 20 LET N=0
- 30 LET M=100
- 40 PRINT: PRINT
- 50 LET R=INT(RND(1)*M+1)
- 60 PRINT "THINK OF A NUMBER"
- 70 PRINT "BETWEEN 1 AND ";M
- 80 LET N=N+1
- 90 PRINT "WHAT'S YOUR GUESS?"
- 100 INPUT G
- 110 IF G=R THEN GOTO 180
- 120 IF G<R THEN PRINT "TRY A BIGGER NUMBER"
- 130 IF G>R THEN PRINT "TRY A SMALLER NUMBER"
- 140 IF N<10 THEN GOTO 80
- 150 PRINT "YOU LOSE"
- 170 STOP
- 180 PRINT "WELL DONE"
- 190 PRINT "YOU GOT IT IN "; N

160 PRINT "THE NUMBER WAS "; R When you run the program, the computer chooses a number between 1 and 100. You have ten chances to guess what it is. If your guess is wrong, the computer tells you whether to pick a bigger or a smaller number next time.

stripes.

Look at the conversion pages


to see if you need

to change any of the lines on grey

How to make the game easier

140 IF N<15 THEN GOTO 80

If you find the game too difficult, change line 140 as shown above. This gives you 15 chances to guess the computer's number.



change. It tells the computer the highest number it can choose.

This is the number to

THINK OF A NUMBER

BETWEEN I AND 100

WHAT'S YOUR GUESS ?

TRY A SMALLER NUMBER

WHAT'S YOUR GUESS?

Another way to make the game easier is to make the computer choose numbers between 1 and 50, or 1 and 20. You can do this by changing the number in line 30 as shown above.

Mindreader THINK OF A NUMBER BETWEEN 1 AND 100 THEN PRESS RETURN DIVIDE THE NUMBER BY 3 WHAT IS THE REMAINDER ?

In Mindreader the computer tells you to think of a number between 1 and 100. Do not type it in, just press RETURN when you have thought of one. To work out the number, the computer asks you for the answers to several sums, so have a pen and paper handy.

Mindreader program

- 10 CLS
- 20 PRINT "THINK OF A NUMBER"
- 30 PRINT "BETWEEN 1 and 100"
- 40 PRINT "THEN PRESS RETURN"
- 50 INPUT R\$:PRINT
- 60 PRINT "DIVIDE THE NUMBER BY 3"
- 70 PRINT "WHAT IS THE REMAINDER?"
- 80 INPUT A
- 90 IF A>=0 AND A<=2 THEN GOTO 110
- 100 GOSUB 280:GOTO 60
- 110 PRINT "DIVIDE THE NUMBER BY 5"
- 120 PRINT "WHAT IS THE REMAINDER?"
- 130 INPUT B
- 140 IF B>=0 AND B<=4 THEN GOTO 160
- 150 GOSUB 280:GOTO 110
- 160 PRINT "DIVIDE THE NUMBER BY 7"
- 170 PRINT "WHAT IS THE REMAINDER?"
- 180 INPUT C
- 190 IF C>=0 AND C<=6 THEN GOTO 210
- 200 GOSUB 280:GOTO 160
- 210 LET D=70*A+21*B+15*C
- 220 IF D<=105 THEN GOTO 240
- 230 LET D=D-105:GOTO 220
- 240 CLS
- 250 PRINT:PRINT:PRINT
- 260 PRINT "YOUR NUMBER IS ";D
- 270 STOP
- 280 PRINT "THAT'S NOT RIGHT"
- 290 PRINT "TRY AGAIN"
- 300 RETURN

Geography quiz

You can test your knowledge of the world with the geography quiz program on the right. The computer asks you for the names of the capital cities of 16 different countries. At the end of the quiz the computer gives you a score. Try running the program and see how many answers you get right.



- 10 CLS
- 20 LET S=0
- 30 DIM A\$(16),B\$(16)
- 40 FOR K=1 TO 16:READ A\$(K):NEXT K
- 50 FOR K=1 TO 16:READ B\$(K):NEXT K
- 60 FOR L=1 TO 16
- 70 PRINT:PRINT:PRINT
- 80 PRINT "WHAT IS THE CAPITAL"
- 90 PRINT "CITY OF "; B\$(L); "?"
- **100 INPUT R\$**
- 110 IF R\$=A\$(L) THEN GOTO 150
- 120 PRINT "NO. THE CAPITAL OF"
- 130 PRINT B\$(L);" IS ";A\$(L)
- 140 GOTO 160
- 150 PRINT "WELL DONE": LET S=S+1
- 160 FOR K=1 TO 1000:NEXT K
- 170 NEXT L
- 180 CLS
- 190 PRINT:PRINT:PRINT
- 200 PRINT "YOU GOT ";S;" CORRECT"
- 210 DATA "COPENHAGEN", "PARIS", "ROME"
- 220 DATA "BRUSSELS", "PEKING", "BONN"
- 230 DATA "STOCKHOLM", "MOSCOW", "CANBERRA"
- 240 DATA "OSLO", "LISBON", "VIENNA", "CAIRO"
- 250 DATA "LONDON", "ATHENS", "MADRID"
- 260 DATA "DENMARK", "FRANCE", "ITALY"
- 270 DATA "BELGIUM", "CHINA", "WEST GERMANY"
- 280 DATA "SWEDEN", "RUSSIA", "AUSTRALIA"
- 290 DATA "NORWAY", "PORTUGAL", "AUSTRIA"
- 300 DATA "EGYPT", "ENGLAND", "GREECE", "SPAIN"

If you have a Spectrum you will need to add an extra line, so look at the conversion pages.



Times table quiz

This program helps you with your maths. It makes the computer test your times tables by setting you ten sums. Each time you run the program, the sums are different. Run the program a few times and see what scores you get.



20 FOR K=1 TO 10

30 CLS

40 PRINT:PRINT:PRINT

50 LET X=INT(RND(1)*12+1)

60 LET Y=INT(RND(1)*12+1)

70 PRINT "WHAT IS ";X;" X ";Y

80 INPUT A

90 IF A=X*Y THEN GOTO 110

100 PRINT "WRONG. IT'S "; X*Y:GOTO 120

110 PRINT "CORRECT": LET N=N+1

120 PRINT:PRINT

130 PRINT "PRESS RETURN"

140 INPUT A\$

150 NEXT K

160 PRINT "YOU SCORED "; N

More birthday facts

230 LET Y=Y1

240 IF M2<M1 THEN LET Y=Y+1

250 IF M2=M1 AND D2<D1 THEN LET Y=Y+1

260 GOSUB 400

270 PRINT "YOUR NEXT BIRTHDAY IS ON A ";D\$(X)

280 LET Q1=D1-31:LET Q2=D2-31

290 FOR K=1 TO M1:LET Q1=Q1+N(K):NEXT K

300 FOR K=1 TO M2:LET Q2=Q2+N(K):NEXT K

310 LET Q=Q1-Q2

320 IF Q>0 THEN LET Q=365-Q

330 IF $Q < \emptyset$ THEN LET Q = ABS(Q)

340 PRINT "IT IS IN"

350 PRINT Q;" DAYS TIME AND"

360 PRINT "YOU WILL BE ";YA+1;" YEARS OLD"

370 STOP

Here are some extra lines to add to the Birthday fact-finder program on page 24. They make the computer tell you all sorts of things about your next birthday. Before you type them in, you need to type in all the program lines on pages 24 and 25.



Remember to check

the conversion pages.

Adding sound and colour

On these two pages there are extra program lines which will add sound effects to the Obstacle course game on page 28 and colour to the Drawing pictures program on page 14. In each case type in the whole program before adding the extra lines for your computer.

Drawing pictures in colour

When you have added the lines, you can change the colour of the star by pressing C and the background colour by pressing P or B (try both).

Commodore 64

25 LET C=14:LET B=14:LET P=6

41 IF A\$="P" THEN LET P=P+1 42 IF A\$="B" THEN LET B=B+1

43 IF A\$="C" THEN LET C=C+1

44 IF P>15 THEN LET P=0


45 IF B>15 THEN LET B=0

46 IF C>15 THEN LET C=0

47 POKE 53281,P

48 POKE 53280,B

95 POKE 55336+X+Y * 40.C



10 GR 25 LET C=17

45 IF A\$="C" THEN LET C=C+17

46 IF C>255 THEN LET C=0 90 COLOR=C:PLOT X,Y

110 COLOR=0:PLOT X,Y

VIC 20

9 INPUT S\$:LET S=PEEK(7748)

25 LET B=4:LET P=1:LET C=6

26 POKE 38400+X+Y*22.C

27 POKE 7680+X+Y * 22,S

41 IF A\$="P" THEN LET P=P+1

42 IF A\$="B" THEN LET B=B+1

43 IF A\$="C" THEN LET C=C+1

44 IF P>15 THEN LET P=0 45 IF B>7 THEN LET B=0

46 IF C>7 THEN LET C=0

47 POKE 36879,(8+16*P+B)

82 PRINT CHR\$(19);

90 POKE 36878,15:POKE 36875,225

92 FOR T=1 TO 100:NEXT T

95 POKE 36875,0 100 GOTO 26

Spectrum

1 LET B=6

2 PAPER B 25 LET C=0

41 IF A\$="P" OR A\$="B" THEN LET B=B+1 43 IF A\$="C" THEN LET C=C+1

45 IF B>7 THEN LET B=0 46 IF C>7 THEN LET C=0

47 BORDER B

90 PRINT AT Y,X;INK C;S\$

BBC and Electron

3 MODE 2

25 LET C=7:LET B=128 26 COLOUR B

42 IF A\$="C" THEN LET C=C+1

43 IF C>7 THEN LET C=0

45 COLOUR C

46 IF A\$="B" OR A\$="P" THEN LET B=B+1

47 IF B>135 THEN LET B=128 48 VDU 19.128.B:0:

36 *On the Apple you cannot change the background colour and the pictures are now drawn with coloured squares.

Sound effects for Obstacle course game

When you add the extra lines to the Obstacle course game, the computer produces a sound effect when you win the game and a different one if you crash.*

Commodore 64

- 50 IF Z(Q,W)=1 THEN GOSUB 400:END
- 60 IF Z(Q,W)=2 THEN GOSUB 200:END
- 200 PRINT CHR\$(19)
- 210 FOR J=1 TO 20:PRINT:NEXT J
- 220 PRINT TAB(15);"WELL DONE"
- 230 POKE 54296,15:POKE 54276,17
- 240 POKE 54277,129:POKE 54278,64
- 250 FOR H=0 TO 200: POKE 54273.H: NEXT H
- 260 POKE 54272,0:POKE 54273,0
- 270 RETURN
- 400 PRINT CHR\$(19)
- 410 FOR J=1 TO 20:PRINT:NEXT J
- 420 PRINT TAB(15);"CRRRAAASH!"
- 430 FOR D=20 TO 0 STEP -1:POKE 54296,D
- 440 POKE 54276,129:POKE 54277,15
- 450 POKE 54273,40:POKE 54272,200:NEXT D
- 460 POKE 54276,0:POKE 54277,0:POKE 54273,0
- 470 RETURN

Apple

- 50 IF Z(Q,W)=1 THEN GOSUB 400:END
- 60 IF Z(Q,W)=2 THEN GOSUB 200:END
- 200 PRINT "WELL DONE!"
- 210 FOR N=1 TO 5:FOR T=1 TO 3
- 220 PRINT CHR\$(135)
- 230 FOR P=1 TO 10:NEXT P
- 240 NEXT T:FOR P=1 TO 50:NEXT P
- 250 NEXT N:RETURN
- 400 PRINT "CRRRAAASH!"
- 410 FOR N=1 TO 100:SOUND=PEEK(-16336)
- 420 NEXT N:RETURN

VIC 20

- 50 IF Z(Q,W)=1 THEN GOSUB 400:END
- 60 IF Z(Q,W)=2 THEN GOSUB 200:END
- 200 PRINT CHR\$(19)
- 210 FOR J=1 TO 20:PRINT:NEXT J
- 220 PRINT TAB(5);"WELL DONE"
- 230 FOR E=1 TO 25:NEXT E
- 240 GOSUB 500: RETURN
- 400 PRINT CHR\$(19)
- 410 FOR J=1 TO 20:PRINT:NEXT J
- 420 PRINT TAB(5); "CRRRAAAASH!"
- 430 POKE 36877,200
- 440 FOR D=15 TO 0 STEP -1:POKE 36878,D
- 450 FOR T=1 TO 40:NEXT T:NEXT D
- 460 POKE 36877,0:POKE 36878,0
- 470 RETURN
- 500 POKE 36878,15:FOR D=130 TO 240
- 520 POKE 36876,D:FOR T=1 TO 5:NEXT T
- 530 NEXT D:POKE 36876,0:POKE 36878,0
- 540 RETURN

Spectrum

- 50 IF Z(Q,W)=1 THEN GOSUB 400:STOP
- 60 IF Z(Q,W)=2 THEN GOSUB 200:STOP
- 200 FOR N=0 TO 50 STEP 2
- 210 BEEP .1, N:BEEP .1, N-2: NEXT N
- 220 PRINT AT 10,9;"WELL DONE"
- 230 RETURN
- 400 PRINT AT 10,9;"CRRRAAASH!"
- 410 FOR N=50 TO 0 STEP -1
- 420 BEEP.1,N:NEXT N
- 430 RETURN

BBC and Electron

- 50 IF Z(Q,W)=1 THEN GOSUB 400:END
- 60 IF Z(Q,W)=2 THEN GOSUB 200:END
- 200 PRINT TAB(5,27)"WELL DONE"
- 210 FOR N=0 TO 120:SOUND 1,-15,N,1
- 220 NEXT N:RETURN
- 400 PRINT TAB(7,27)"CRRRAAASH!"
- 410 FOR N=0 TO 120:SOUND 1,-15,120-N,1
- 420 NEXT N:CLS:RETURN

^{*}To hear the sound effects on the Commodore 64 and VIC 20 you may need to adjust the TV's volume control.

Puffing train graphics


Below and on the next page are lines to add to the Puffing train program on page 20. They make the computer draw a coloured train, and as it puffs along you can make it whistle by pressing the W key.

The lines are different for each computer, so make sure you type in the right ones for yours. Remember, too, that you must type in all the program lines on pages 20-21 before adding the extra lines.

The train shape is made up of lots of blocks which are called graphics characters. You need a colour TV or monitor, to show the train in colour.

BBC and Electron

- 2 MODE 1:COLOUR 130
- 4 VDU 23,224,255,255,255,255,255,255,255
- 6 VDU 23,225,225,255,255,255,0,0,0,0
- 8 VDU 23,226,0,0,0,0,255,255,255,255
- 12 LET T\$=CHR\$(224)+CHR\$(224)+CHR\$(224)+CHR\$(224) +CHR\$(224)+CHR\$(224)+CHR\$(224)+CHR\$(32)
- 14 LET T1\$=CHR\$(32)+CHR\$(224)+CHR\$(224) +CHR\$(32)+CHR\$(32)+CHR\$(226)+CHR\$(32) +CHR\$(32)+CHR\$(224)+CHR\$(32)
- 16 LET T2\$=CHR\$(32)+CHR\$(32)+T\$
- 18 LET T3\$=CHR\$(32)+CHR\$(224)+T\$
- 22 COLOUR Ø
- 25 PRINT TAB(X,9)CHR\$(225)
- 45 COLOUR 1
- 50 PRINT TAB(X)T1\$
- 60 PRINT TAB(X)T2\$
- 70 PRINT TAB(X)T3\$
- 75 COLOUR Ø
- 120 SOUND 1,-9.0,1
- 122 SOUND 1,-9,5,1
- 123 LET A\$=INKEY\$(0)
- 125 IF A\$="W" THEN VDU 7





Apple


The lines below make the Apple produce the train's whistle. There are no graphics instructions because they are very complicated and would take a long time to type in.

- 114 GOSUB 500
- 120 A\$="":IF PEEK(-16384)>127 THEN GET A\$
- 125 IF A\$<>"W" THEN GOTO 130
- 126 PRINT CHR\$(135):FOR N=1 TO 100
- 127 NEXT N:PRINT CHR\$(135)
- 500 FOR T=1 TO 10:SOUND=PEEK(-16336)
- 510 FOR Q=1 TO RND(1)*15:NEXT Q
- 520 NEXT T: RETURN

Commodore 64







Program conversions: BBC and Commodore 64

Here and on the next few pages are lines you may need to type instead of those on red (or grey) stripes. To find a line, look in the section for your computer and find the name and page number of the program you are typing in. Then look for a line with the same number as the one on the stripe. If you cannot find one, you can type the line on the stripe just as it is.

BBC conversions

Page 14
Drawing pictures
30 LETA\$=INKEY\$(0)

Page 16 Computer Snap 60 LET A\$=INKEY\$(0)

Page 21
Puffing train program
Changing direction
140 LET A\$=INKEY\$(0)

Page 28
Obstacle course game
70 LET A\$=INKEY\$(0)

Page 31 Find the key 40 LET A\$=INKEY\$(0) 70 LET S=INT((N/316)*10)/10

Commodore 64 conversions

Page 7 Special words 10 PRINT CHR\$(147)

Page 8 Happy Birthday 10 PRINT CHR\$(147)

Page 10 Space monsters 10 PRINT CHR\$(147)

Page 11
Making the monster move
120 PRINT CHR\$(147)

Page 12 Red Alert 10 PRINT CHR\$(147)

Page 13
Personal messages
2 PRINT CHR\$(147)

Page 14
Drawing pictures
10 PRINT CHR\$(147)

30 GET A\$ 82 PRINT CHR\$(19)

84 FOR K=1 TO Y:PRINT:NEXT K

90 PRINT TAB(X);" * "

Page 15
Rubbing out stars
110 PRINT TAB(X);" "

Patterns with different symbols


3 PRINT CHR\$(147) 90 PRINT TAB(X);S\$

Page 16 Computer Snap

10 PRINT CHR\$(147)

60 GET A\$





Program conversions: Electron and VIC 20

Electron conversions

Page 14 Drawing pictures

30 LET A\$= INKEY\$(0)

Page 16 Computer Snap 60 LET A\$=INKEY\$(0) You should add this line to the program

Page 21

Puffing train program Changing direction

140 LET A\$=INKEY\$(0)

Page 28

Obstacle course game

Page 31 Find the key 40 LET A\$=INKEY\$(0)

VIC 20 conversions

Page 7 Special words 10 PRINT CHR\$(147)

Page 8
Happy Birthday
10 PRINT CHR\$(147)

Page 10 Space monsters 10 PRINT CHR\$(147)

Page 11
Making the monster move
120 PRINT CHR\$(147)

Page 12 Red Alert 10 PRINT CHR\$(147)

Page 13 Personal messages 2 PRINT CHR\$(147)

Page 14
Drawing pictures
10 PRINT CHR\$(147)

30 GET A\$ 82 PRINT CHR\$(19)

84 FOR K=1 TO Y:PRINT:NEXT K

90 PRINT TAB(X); "*"

Page 15
Rubbing out stars
110 PRINT TAB(X);" "

Patterns with different symbols

3 PRINT CHR\$(147) 90 PRINT TAB(X):S\$

Page 16 Computer Snap

10 PRINT CHR\$(147)

60 GET A\$

Page 18 Code-writer

10 PRINT CHR\$(147) 100 PRINT CHR\$(147) Each time you see this symbol, you should press this key with SHIFT.

Page 20 Puffing train program

10 PRINT CHR\$(147)

20 LET A=0:LET B=10:LET C=1

40 PRINT CHR\$(19)

45 PRINT:PRINT:PRINT:PRINT

90 PRINT "fffff"; TAB(X+7); "□*□"

100 IF X/2=INT(X/2) THEN PRINT " 1 "; TAB(X+8); "*"

110 PRINT "†";TAB(X);"□"



Page 21 Adding a railway track

24 PRINT CHR\$(19):FOR Y=1 TO 8:PRINT:NEXT Y 25 PRINT TAB(X):"="

Changing direction

117 PRINT "†";TAB(X+16);"□"
140 GET A\$

Add line 24 to the program.

Page 22

Computer postcard

10 PRINT CHR\$(147) 110 PRINT CHR\$(147)

Page 24 Birthday fact-finder

10 PRINT CHR\$(147):DIM N(12)

Page 26 Star racer

10 PRINT CHR\$(147)

40 PRINT:PRINT TAB(0);K

59 PRINT CHR\$(19)

70 PRINT:PRINT TAB(X(K));" *"

80 IF X(K)=19 AND Y=0 THEN LET Y=K

Add line 59 to

the program.

120 IF Y=0 THEN GOTO 59

Page 27 Adding a race track

51 PRINT CHR\$(19)

53 FOR L=1 TO 21

Race game

28 PRINT CHR\$(147):LET Y=0

Page 28 Obstacle course game

10 LET A=20:LET B=20

15 LET Z\$=CHR\$(18)+CHR\$(160)+CHR\$(146)

20 PRINT CHR\$(147):DIM Z(A,B)

40 PRINT CHR\$(19)

43 FOR K=1 TO W:PRINT:NEXT K

45 PRINT TAB(Q);"*"

70 GET A\$

100 LET Z(X,Y)=1:PRINT CHR\$(19)

103 FOR K=1 TO Y:PRINT:NEXT K

105 PRINT TAB(X); Z\$

Page 29

Improving the game
34 IF Z(K,L)=1 THEN GOSUB 150

150 PRINT CHR\$(19)

160 FOR J=1 TO L:PRINT:NEXT J

170 PRINT TAB(K); Z\$

180 RETURN

Add these extra lines to the program.

Page 31 Find the key

10 PRINT CHR\$(147):LET N=0:LET A=ASC("A")

40 GET A\$

70 LET S=INT((N/140)*10)/10

Page 32

Guess the number

10 PRINT CHR\$(147)

Page 33 Mindreader

10 PRINT CHR\$(147)

240 PRINT CHR\$(147)

Page 34

Geography quiz

10 PRINT CHR\$(147)

180 PRINT CHR\$(147)

Page 35

Times table quiz 30 PRINT CHR\$(147) There are five

extra lines

here. Make sure you add

them to the

program.

Program conversions: Spectrum

Page 8 Happy Birthday

50 PRINT A\$(K TO K);

You should add this line to the program.

Page 14 Drawing pictures

35 FOR K=1 TO 15:NEXT K -90 PRINT AT Y, X;"*"

Page 15 Rubbing out stars

110 PRINT AT Y,X;" "

Patterns with different symbols

90 PRINT AT Y,X;S\$

Page 16 Computer Snap

30 LET X=INT(RND * 10+1) 40 LET Y=INT(RND * 10+1)

Page 17 Word and number snap

2 DIM N\$(10,5)

Page 18 Code-writer

70 LET C\$=C\$+M\$(K+1 TO K+1) 80 LET C\$=C\$+M\$(K TO K)

Page 20 Puffing train program

20 LET A=0:LET B=20:LET C=1

40 PRINT AT 4,0

90 PRINT AT 4.X+7:"□ * □"

100 IF X/2=INT(X/2) THEN PRINT AT 3,X+8;"*"

110 PRINT AT 3,X;"""

Page 21 Adding a railway track

25 PRINT AT 9.X:"="

Changing direction

117 PRINT AT 3,X+16:""

Page 23 Writing thank-you letters

165 LET R=INT(RND * 5+1)

Page 25 Day-finder

15 DIM D\$(8,9)

Page 26 Star racer

40 PRINT AT K+K,1;K

70 PRINT AT K+K,X(K):"

80 IF X(K)=30 AND Y=0 THEN LET Y=K

90 LET R=INT(RND * 2+1)

Page 27 Adding a race track

51 PRINT AT 0.0 53 FOR L=1 TO 31

Race game

57 PRINT G1 59 PRINT G2 Add these two lines to the program.

This extra line

until you get

to the end.

Page 28 Obstacle course game

10 LET A=30:LET B=20:LET Z\$=CHR\$(143)

40 PRINT AT W.Q:"\"

80 LET X=INT(RND * A+1)

90 LET Y=INT(RND * B+1)

100 LET Z(X,Y)=1:PRINT AT Y,X:Z\$

Page 29 Improving the game

32 LET Z(A,INT(RND * 15+3))=2

34 IF Z(K,L)=1 THEN PRINT AT L,K;Z\$

Page 31 Find the key

10 CLS:LET N=0:LET A=CODE("A")

20 LET X=INT(RND * 26+A)

70 LET S=INT((N/77) * 10)/10

103 PAUSE 20

Page 32 Guess the number continues below.

50 LET R=INT(RND * M+1) Don't press ENTER

Page 34 Geography quiz

30 DIM A\$(17,10):DIM B\$(17,15) 105 IF LEN(R\$)<10 THEN LET R\$=R\$+</p>

" ":GOTO 105

Page 35 Times table quiz

50 LET X=INT(RND * 12+1)

60 LET Y=INT(RND * 12+1)

Program conversions: Apple

Page 7 Special words 10 HOME

Page 8 Happy birthday 10 HOME

Page 10 Space monsters 10 HOME

Page 11 Making the monster move 120 HOME

Page 12 Red Alert 10 HOME

Page 13 Personal messages 2 HOME

Page 14 **Drawing pictures** 10 HOME

30 A\$="":IF PEEK (-16384)>127 THEN GET A\$ 90 VTAB(Y):HTAB(X):PRINT "%"

Page 15 Rubbing out stars 110 VTAB(Y):HTAB(X):PRINT " "

Patterns with different symbols

3 HOME 90 VTAB(Y):HTAB(X):PRINT S\$

Page 16 Computer Snap 10 HOME

60 A\$="":IF PEEK(-16384)>127 THEN GET A\$

Page 18 Code-writer 10 HOME 100 HOME

Page 20 Puffing train program

10 HOME 20 LET A=1:LET B=29:LET C=1

40 VTAB(5):HTAB(1)

90 VTAB(4):HTAB(X+7):PRINT "□*□"

100 IF X/2=INT(X/2) THEN VTAB(3):. HTAB(X+8):PRINT "*"

110 VTAB(3):HTAB(X):PRINT ""

This line continues below. Don't press RETURN until you get to the end.

Page 21 Adding a railway track 25 VTAB(9):HTAB(X):PRINT "="

Changing direction 117 VTAB(3):HTAB(X+16):PRINT "" 140 A\$="":IF PEEK(-16384)>127 THEN GET A\$

Page 22 Computer postcard 10 HOME 110 HOME

Page 24 Birthday fact-finder 10 HOME: DIM N(12)

Page 26 Star racer

10 HOME

40 VTAB(K+K):HTAB(1):PRINT K

70 VTAB(K+K):HTAB(X(K)):PRINT " *"

Page 27 Adding a race track 51 VTAB(1):HTAB(1)

Race game 28 HOME:LET Y=0

Apple conversions

Page 28 Obstacle course game

10 LET A=39:LET B=23:LET Z\$="0"

20 HOME:DIM Z(A,B)

40 VTAB(W):HTAB(Q):PRINT "*"

70 A\$="":IF PEEK(-16384)>127 THEN GET A\$

100 LET Z(X,Y)=1

105 VTAB(Y):HTAB(X):PRINT Z\$

Page 29 Improving the game

34 IF Z(K,L)=1 THEN VTAB(L):HTAB(K):PRINT Z\$

Page 31 Find the key

10 HOME:LET N=0:LET A=ASC("A")

40 A\$="":IF PEEK(-16384)>127 THEN GET A\$

70 LET S=INT((N/56) * 10) / 10

Page 32 Guess the number 10 HOME

Page 33

Mindreader 10 HOME

240 HOME

Page 34 Geography quiz

10 HOME 180 HOME

Page 35 Times table quiz 30 HOME

Key chart


This chart shows the names that the different computers give to the RETURN, ESCAPE and DELETE keys. When you are told to use one of these in this book, you should press your computer's key.


*There is also a BREAK key, but do not use it because it wipes the program from the computer's memory.

Names used in this book	RETURN	ESCAPE	DELETE
ввс	RETURN	ESCAPE *	DELETE
Electron	RETURN	ESCAPE *	DELETE
VIC 20	RETURN	RUN STOP	INST DEL
Commodore 64	RETURN	RUN STOP	INST DEL
Apple	RETURN	CTRL C Press both these keys together.	\leftarrow
Spectrum	ENTER	CAPS SHIFT SPACE Press both these keys together.	CAPS SHIFT Ø— Press both these keys together.


Bug-spotting guide

If a program does not work, it usually means there is a mistake or bug in it. The computer may display an error message which tells you what sort of mistake it is and what line it is in. If not, list the program and check each line very carefully. Even tiny bugs can stop a program working. There are some hints for what to look for below.







Make sure that you have made all the line changes needed for your computer. Check the lines on stripes against the conversions for your computer.




Look out for simple typing mistakes in BASIC commands. The computer will not understand if you spell these wrongly.



Check for missing quotation marks. It is very easy to forget these when you are typing a program and it confuses the computer.



Make sure that you have put in all the punctuation marks. They are very important in BASIC as they have special meanings.



Check that you have typed all the numbers with the number keys. It is very easy to muddle the number 0 with the letter O.



If you still cannot find a bug, try retyping the longer or more complicated lines again. You might correct a mistake you have not noticed.

Index

BASIC, 34, Birthday fact-finder main program, 24 more birthday facts, 35 BREAK, 9, 46 bugs, 6, 47	Geography quiz, 34 getting rid of programs, 5 graphics characters, 38 Guess the number, 32 Happy birthday program, 8	Postcard program, 22 PRINT, 4 program, 4 how to type in, 4-5 Puffing train program main program, 20 graphics, 38	
changing programs, 7 Code-writer program, 18 colour, 36	INPUT, 4	Race game, 27	
conversions, 40-46 how to make, 7 cursor, 4	key chart, 46	Red Alert program, 12 RETURN, 4, 46 RUN, 5 running programs, 5	
	LIST, 6		
de-bugging a program, 6, 47 DELETE, 5, 46 Drawing pictures main program, 14 in colour, 36	Mindreader program, 33 mistakes, 6 how to correct, 6, 47	saving programs on tape, 23 Snap program, 16 sound effects, 37 Space monsters program, 10 Star racer program, 26	
ENTER, 4, 6, 46	NEW, 5	stopping programs, 9	
error messages, 6, 47 ESCAPE, 9, 46	Obstacle course game	TAB, 12 Thank-you letter program, 23	
Find the key program, 31	main program, 28 sound effects, 37	Times table quiz, 35 typing in programs, 4	

First published in 1984 by Usborne Publishing Ltd, 20 Garrick Street, London WC2E 9BJ, England.


© 1984 Usborne Publishing Ltd.

The name Usborne and the device are Trade Marks of Usborne Publishing Ltd.

All rights reserved. No part of this publication may be reproduced, stored in a retrieval system or transmitted in any form or by any means, electronic, mechanical, photocopying, recording or otherwise, without the prior permission of the publisher.

FIRST COMPUTER LIBRARY

The First Computer Library is a lively and colourful new series for young beginners to computing. A gang of friendly ghosts and monsters show the reader what computers can do, how they work and how to program them. The books are packed with short, entertaining programs which will run on most makes of home computer.



All About Computers

This colourful introduction explains in simple terms what a computer is, how it works and what it can do. Short programs are included to illustrate the explanations.



Simple BASIC

A simple and fun introduction to programming in BASIC, with masses of entertaining programs to try and puzzles to solve.



Computer Fun

This book is packed with programs to make a computer flash messages, play games, make pictures and lots besides. No previous programming knowledge is needed.

The Usborne First Guide to the BBC Micro

This friendly guide for young readers explains exactly how to set up and use a BBC computer. A group of little monsters explain how to program in BBC BASIC, give helpful advice on things that can go wrong and show what the BBC micro can do.



IZBN 0-8P050-803-P

